
Software Release Notes

SetraEDGE Version 2.1.0

This document provides the changes to SetraEDGE Software version 2.10

Purpose of the Release

The purpose of this document is to communicate major new features, changes, and solved bugs in this release of SetraEDGE software. It may also document workarounds and any feature restrictions.

Software Updates

- Added Error Status checkboxes for Modbus and BACnet SPC device types enabled by default
- Improved dropdown to show only relevant device types.
- Updated communication options to display MQTT as the sole option.
- Installation Report can now be downloaded from the System page
- The latest EDGE log messages are now visible on the System page without downloading logs
- Installation Report includes all device configurations
- Ensured proper configuration of Inbound communication types
- All devices are displayed simultaneously in the system view

Solved Software Bugs

- The default setting now uses network date and time and works more consistently
- Exporting installation records no longer requires entering Notes
- Fixed temperature unit change issue for particle counter
- Resolved message truncation in the Edge portal
- Multiple EDGE devices can now be used on the same local network
- Fixed issue allowing invalid values for BACnet Instance
- Corrected user deletion issue in the Edge user group

Improvements

- Added Scaling option for temperature and relative humidity in SRF 613 for better data configuration
- Prevented entry of invalid values for BACnet Instance and numeric fields

NOTE: A software update versioned 2.0.0 or greater is not compatible with SetraEDGE 1.0 hardware. If you have questions regarding your SetraEDGE hardware, please contact your Regional Sales Manager or email SetraCEMS@setra.com.